

**FLOWERS**- 15/0 Color A beads/Color B beads/26 gauge red or gold wire

**Technique:** - Continuous Wrap-Around Loops, Cross-Over Scallop (COS)

**Pattern:** - Seven Quadruple 10-bead Continuous Wrap-Around Loops with **pointed bottoms** - 4<sup>th</sup> loop: COS at middle

**Loop 1** - 4 B, 2 A, 4 B

**Loop 2** - 6 B, 7 A, rest B

**Loop 3** - 9 B, 10 A, rest B

**Loop 4** - COS middle: fill A, 2 B, COS, 2 B, rest A

1. Cut 46 inches (116 cm) of 26 gauge wire off the spool.

2. **Loop 1:** String on Loop 1 beads - 4 B, 2 A, 4 B. Leaving a 2 inch (5 cm) tail, make a loop. *Photo 14.*

3. **Loop 2:** String on Loop B beads - 6 B, 7 A, rest B. Make double a wrap-around loop. *Photo 15.*

4. **Loop 3:** String on Loop C beads. 9 B, 10 A, rest B. Make triple wrap-around loop. *Photo 16,*

5. **Loop 4:** We're making a Continuous-Cross Over Scallop along the top middle. String and fill Color A up to the middle top of the unit. *Photo 17.*

6. Remove 2 Color A and replace with 2 Color B beads. *Photo 18.*

7. Maneuver the working-wire behind the unit (*Photo 19*) and thread it up between the two outer rows in between two beads along the middle of the top row. *Photo 20.*

8. String on 2 Color B beads and the rest A to finish quadruple wrap-around loop. *Photo 21.* See finished Flower unit in *Photo 22.*

**Note:** for a different colorway, switch Color A & B.

- Make 3 **Flowers.**



Photo 14



Photo 15




Photo 16



Photo 17



Photo 18



Photo 19



Photo 20



Photo 21



Photo 22

## FLOWER ASSEMBLY

**PREPARE:** Prepare 3 lengths of 18 gauge stem wires by wrapping the top inch with floral tape.

1. Insert the **Center** into the **Flower**. *Photo 23.*  
Twist the tail wires at the base.

2. Insert the stem wire into the hole of the flower.  
Wrap the stem with floss down about  $\frac{3}{4}$  inch (1.9 cm). *Photo 24.*

3. Position the **Calyx** so that the tip of the units are at the base of the flower. Adjust the flossing if needed if you've flossed too much. Leave the **Calyx** open. Wrap the tail wires in with the floss. *Photo 25.*

4. Floss down the stem about 3 inches (7.6 cm).

5. Floss in **Leaf Stem A** and a **Bud OR Budding Flower** leaving about  $\frac{1}{4}$  inch (.6 cm) in between. Cut and knot the floss. Secure with floral tape.

6. Close the **Calyx** by lacing the first and last unit together. *Photo 26.*

Assemble 3 Flower Stems.



Photo 23



Photo 24



Photo 25



Photo 26