
PRACTICE LEAVES - 11/0 green beads/24 gauge green wire

Technique: Double Split Basic

Pattern: 3-bead double split basic (DSB), PT PB, 11 rows - make 7

PREPARE: String green beads onto a spool of green wire. Approx. 22 inches (56 cm) beads per Leaves set.

- 1. **Double Split Basic**. Make a basic frame with 3 beads for the basic row and 3 beads in the basic loop with a 4 inch (10.1 cm) twisted wire/loop. *Photo 1.*
- 2. Make the first 3 rows and then start lace-as-you-go along the middle. *Photo 2*. Make the leaf according to the **Leaves A** pattern above.
- 3. Move the 3 beads in the loop to one side. Cut along the top so that there are two wires. *Photo 3*. Knot the wire with the beads. The other wire is now one of the ending tail wires.
- 4. Twist the working-wire and the wire with the beads together to form another twisted wire. *Photo 4.* TIP: Measure the twisted wire from the first leaf to get the length for the second twisted wire.
- 5. Make the second leaf according to the **Leaves** A pattern. Cut another tail off of the spool. *Photo 5*.





PRACTICE LEAVES - 11/0 green beads/24 gauge green wire

Technique: Triple Split Basic

Pattern: 3-bead triple split basic (TSB), two leaves with 9 rows and one leaf with 7 rows, PT PB

PREPARE: String green beads onto a spool of green wire. Approx. 22 inches (56 cm) beads per Leaves set.

- I. **Triple Split Basic**. Make a basic frame with 3 beads for the basic row and 6 beads in the basic loop with a 4 inch (10.1 cm) twisted wire/loop. Start **lace-as-you-go**.
- 2. Make the first leaf with 9 rows. Divide the beads so there are 3 on each side of the loop. Cut at the top. *Photo 1.* Knot the ends.
- 3. Twist the working-wire and one of the cut wires to form a new twisted wire. Make another leaf with 9 rows.
- 4. Twist the working-wire and the last cut wire together to form another twisted wire. TIP: To get the right length for the 3rd twisted wire, make one twist less than the first two twisted wires. *Photo 2.*
- 5. Make a leaf with 7 rows. Cut a tail off the spool.
- 6. With the triple split basic, there is only one bottom wire. To end up with two bottom wires, take a 3 inch (7.6 cm) length of wire, hook ¼ inch (.6 cm) of the wire in between two leaves. *Photo 3.* NOTE: Having two bottom wires help the stability of the stem when assembled.
- 7. Twist the wires together. Now there are two bottom wires. *Photo 4.*
- 8. Shape the leaves.

